

MeVisLab Scientific3DFigurePDFApp Manual

Table of Contents

- [Purpose](#)
- [Usage](#)
- [Details](#)
 - [Creating U3D Model Files](#)
 - [Assembling the Model](#)
 - [Editing Point Sets](#)
 - [Editing Line Sets](#)
 - [Editing Meshes](#)
 - [Creating Views](#)
 - [Saving the Model to U3D](#)
 - [Creating Poster Images](#)
 - [Editing the PDF Page](#)
- [Tips](#)

Purpose

This module provides an integrated application for creating two types of files:

- U3D files which can be embedded into Portable Document Format (PDF) for creating interactive figures and
- a PDF document with pre-defined layout which includes such an embedded interactive figure.

Usage

The creation of PDF documents is done entirely on the "PDF Page" tab (see Details section below).

For creating U3D files, there are two approaches:

- connecting input data to the four input connectors or
- assembling the data with the build in assistant (Tab "3D Model" -> Tab "Assemble Model").

The input connectors work as described for the SaveU3D module (please refer to the MeVisLab documentation of that module for details). Assembling the module by means of the assistant is described in the "Details" section below.

Details

Creating U3D Model Files

Universal 3D (U3D) is a compressed file format standard for 3D computer graphics data which is standardized by Ecma International as [ECMA-363](#). This module internally uses the SaveU3D module for creating the U3D files.


Select the "3D Model" tab to create a U3D file.

Input data can be collected in two ways: either by feeding it to the input connectors or by assembling it by means of the built-in assistant. The former way is for experienced MeVisLab users and allows for attaching this macro at the end of a processing chain. Enable the Use Input Connectors checkbox if you want to use this option. In order to assemble the model by means of the built-in assistant, enable the Load Data Manually checkbox.


Assembling the Model

Using Input Connectors

If the Use Input Connectors checkbox is enabled, the model data is loaded from the input connectors and all controls on the *Assemble Model* tab are disabled. In this case, the *Assemble Model* tab can only be used to preview the model.



Manual Assembling




The model can also be assembled manually by importing each object step-by-step. Go to the *Assemble Model* tab to assemble the model manually.

Three types of geometries can be imported: point clouds, line sets and meshes.

Each type of geometry has its own box of controls to import. The first step is always to load the object by means of the appropriate *Load {Points|Lines|Mesh} Object* button. After successfully loading the object, it is shown highlighted in the preview area, while all previously added objects are displayed faded. If you are happy with the object, click *Add Imported Model* in the *Add Object* box. It is then permanently added to the model. If you do not want to add a loaded object, click *Unload* in the appropriate box. All models of a kind can be removed at once by means of the appropriate button in the *Remove Objects* box. It is not possible to remove a specific object.

Each type of geometry has its specific import options:

Point Set Import



Point Sets can be imported from text files, e.g., CSV files. A point set definition shall start with a header which consists of an identifier and a numerical value:

```
Points 1
```

The identifier which is used for filtering point sets out of a larger file can be specified by means of the *ID* field. By default it is "Points".

The header can also have an optional name. Everything after the numerical value is interpreted as name:

```
Points 1 Anchor Points
```


The point set definition shall then continue with the coordinates of each point. Each coordinate shall consist of three values (x, y, z) and be listed in a separate line. The values can be separated either by a semicolon (";") or by a space. The decimal delimiter shall be a decimal point ("."):

```
78.873;-30.2173;-109.254 or 63.9515 -16.5974 -76.5908
```

A full Point Set definition typically looks like this:

```
Points 1 Anchor Points
78.873;-30.2173;-109.254
63.9515;-16.5974;-76.5908
41.5693;-7.5175;-54.8151
26.6479;-10.6914;-47.1012
7.99605;-19.9401;-20.2392
```

Line Set Import



Just like Point Sets, Line Sets can be imported from text files (CSV etc.) as well. A Line Set definition shall also start with a header, just like a Point Set definition:

Lines 1 OR Lines 1 Centerline

The default identifier for filtering line sets is "Lines".

The Line Set definition shall then continue with two lists: a list of positions and a list of connections.

The list of positions shall be a list of coordinates that define the positions in the model space that are touched by a line. These positions must be specified just like the Point Set positions described above.

The list of connections shall be a list of pairs, where every pair specifies the indices of two positions that are connected by one segment of a line. The pairs must be integer numbers and can be separated either by a semicolon (";") or by a space:

0;1 OR 5 8


The numbering of indices starts with "0", so the index of the first position in the positions list is "0". The list of connections can be omitted. If no list of connections is provided, all positions of the list of positions are connected automatically, in order of their appearance.

A full Line Set definition (with three line segments) typically looks like this:

```
Lines 1 Axes
31 -144 1118
154 -144 1118
92 -209 1118
92 -78 1118
92 -144 899
92 -144 1338
0 1
2 3
4 5
```

Mesh Import

Meshes can be imported from a number of formats. See the MeVisLab documentation of the [WEMSceneLoader](#) module for a full list of supported formats.



After loading a mesh, the number of faces can be reduced before it is added to the model. Click the *Use Reduced Mesh* button and adjust the reduction ratio by means

of the *Reduction %* field or the slider below the field. (Note that the mesh is updated on-the-fly which can take a while for large meshes. If the update is too slow, use the numerical field instead of the slider.)


Adding the Imported Object

After importing an object, click the *Add Imported Object* button in the *Add Object* box to permanently add the object to the model.

Deleting all Objects of a Kind

All models of a kind can be removed at once from the model by means of the appropriate button in the *Remove Objects* box. It is not possible to remove a specific object from the model.

Editing Point Sets




Go to the *Edit Points* tab to edit Point Sets.

Point Sets can only be edited as regards their name and their group path in the model object tree.

If no name is specified, the default name "PointSet" is assigned. Names do *not* have to be unique, and they may contain space characters. For example, two different objects with the name "My Points" are allowed.

The group path specifies the path where the object is placed in the 3D model tree. All necessary sub-branches are created automatically. Path elements must be separated by a slash ("/") character.

Editing Line Sets




Go to the *Edit Lines* tab to edit Line Sets.

Line Sets can be edited as regards their name (see above), their group path (see above) and their color.

In order to specify an individual color for a line set, uncheck the *Use Default Color* option and select the desired color by means of the *Color* field. The default color is black (RGB 0, 0, 0).

Note that unselected line sets are rendered in light grey (RGB 0.792, 0.792, 0.792), so if you assign this color to the active line set, it will not be possible to distinguish it from the other line sets in preview.


Editing Meshes



Go to the *Edit Meshes* tab to edit meshes.

In addition to name, group path and color, meshes can also be assigned an opacity value. Meshes with an opacity of 1 will be rendered completely opaque, and meshes with an opacity of 0 will be invisible. The default opacity is 1.

Creating Views



Go to the *Create Views* tab to create Views.

A View is a predefined setting that specifies how the objects and the environment shall be rendered.

A view must have a name, which does *not* need to be unique. However, views with identical names could confuse the consumer of a figure, so they should be avoided.

The most important setting for the view will be the camera setting which is specified directly in the *Scene* box. You can interactively rotate, pan and zoom the scene in the *Scene* box and thus select the projection angle. When the View is added (see *Add New View* button below), the camera settings for the View are calculated from the currently selected projection in the *Scene* box. (Note that there might be tiny deviations due to floating point tolerance. However, this usually affects only very small objects.)

In addition to the camera, a *Background Color*, a *Lighting Scheme* and a *Render Mode* can be specified. (Note that the appearance of the latter 2 strongly depends on the PDF rendering engine and that they are therefore not illustrated in the *Scene* preview.)

The *Lighting Scheme* specifies the ambient light which is use to illuminate the scene. See the [PDF Specification](#) (section 9.5.3, p. 817) for details.


The *Render Mode* specifies how objects are rendered. See the [PDF Specification](#) (section 9.5.3, p. 813) for details (or just try them...).

After all settings have been done, click the *Add New View* button to add the specified View to the list of all views. An arbitrary number of views can be added, but remember that they should have unique names. Once added, the Views can still be edited manually in the *All View Specifications* box, but this should only be done very carefully, especially as regards the camera parameters.

In order to delete all views, click the *Delete All Views* button. In order to delete a single View, remove it manually by means of the *All View Specifications* box.

If no view is specified, the PDF generator will create a default view.


Saving the Model to U3D



In order to finally save the U3D file, click the *Save Model* button on the *Save Model* tab. This will open a dialog where you can select a file name. If the selected file name does not have an ".u3d" extension, this extension will be added automatically. Click the *Save* button of the dialog to save the U3D file.

For your convenience, the selected file name will automatically be added to the respective field on the *PDF Page* specification tab.

Creating Poster Images



PDFs allows for replacing 3D figures with a "poster image" that is displayed if the 3D figure is deactivated or if the reader software is not capable of rendering 3D scenes. In order to create such a poster image in PNG format, go to the *Create Poster Image* tab, select the *Poster Background* color and a *Poster Text*, which shall be superimposed. (Note that the poster text is not displayed in the *Preview* box.)

Then, adjust the scene in the *Preview* box, select the objects to show and the *Points Size*.

Finally, click *Save Poster*. This will open a dialog where you can select a file name. If the selected file name does not have a ".png" extension, this extension will be added automatically. Click the *Save* button of the dialog to save the poster image file.

For your convenience, the selected file name will automatically be added to the respective field on the *PDF Page* specification tab.

Editing the PDF Page

In order to create a PDF file with an embedded 3D figure, go to the *PDF Page* tab.

The screenshot shows a web interface for editing a PDF page. It has two tabs: "3D Model" and "PDF Page", with "PDF Page" selected. The interface is divided into three main sections:

- Page Header:** Contains two text input fields. The first is labeled "Header Citation Text:" and contains the text "Newe (2015). 'Fancy article title'. Journal.". The second is labeled "Header Headline Text:" and contains "Additional Figure S1 - Interactive 3D PDF". Below these fields is a checked checkbox labeled "Include instructional hints above the figure".
- 3D Figure:** Contains several fields: "U3D Filename:" with a text input field containing "D:/MyArticles/FancyArticleTitle/3D-Models/model.u3d" and a "Browse..." button; "Poster Image Filename:" with a text input field containing "D:/MyArticles/FancyArticleTitle/3D-Models/model.png" and a "Browse..." button; "Activation Mode:" with a dropdown menu set to "User activate (recommended)"; "Deactivation Mode:" with a dropdown menu set to "User deactivate (recommended)"; "Toolbar Enabled:" with a checked checkbox; "Navigation Interface Enabled:" with an unchecked checkbox; and "Animation Autostart:" with an unchecked checkbox.
- Description:** Contains a "Caption:" field with the text "Model of an anatomic structure." and a larger "Description:" text area containing several lines of Lorem Ipsum placeholder text.

At the bottom of the interface is an "Output" section with a "Save PDF" button.

Each PDF page created by this module consists of three part: a header, the interactive figure itself and the figure description.

Page Header

The page header consists of a Header Citation Text and a Header Headline Text.

The Header Citation Text is displayed on top of the page and should usually contain information about the article to which the PDF is related to. Alternatively, this line could also contain information about the authors, their institution or something similar. However, the text should fit in three lines, because everything else will be truncated.

The Header Headline Text is displayed in large, bold font below the Header Citation Text and should be rather short since it must fit in one line. (The actual Caption of the figure has its own field, see below.)

The page header can be complemented by a pre-defined instructional text which explains how to use the interaction features in Adobe Reader. Enable the *Include instructional hints above the figure* checkbox to include these instructions.

3D Figure

The actual 3D figure will be included below the Header Headline Text or the instructional text, respectively. It will have a fixed 4:3 ratio. The U3D file which shall be included can be specified by means of the *U3D Filename* field. This field is mandatory - if no U3D file is specified, it will not be possible to create a PDF.

The poster image which shall be displayed if the 3D figure is deactivated or if the reader software is not capable of rendering 3D scenes can be specified by means of the *Poster Image Filename* field. This field is not mandatory and can be left empty. If no poster image is provided, the default text of the reading software will be displayed.

(The two filename fields will be pre-configured if you have previously used the macro to create the U3D file and/or the poster image file.)

Besides the file names, 5 options can be configured:

- *Activation Mode*: Specifies whether the 3D figure shall be activated manually or automatically.
- *Deactivation Mode*: Specifies whether the 3D figure shall be deactivated manually or automatically.
- *Toolbar Enabled*: Specifies whether the 3D toolbar shall be visible if the 3D figure is enabled.
- *Navigation Interface Enabled*: Specifies whether the navigation interface shall be visible if the 3D figure is enabled. The navigation interface enables the consumer of a PDF to interactively select which objects of the 3D figure shall be displayed.
- *Animation Autostart*: Specifies whether animations shall be started automatically if the 3D figure is enabled. (Note that the creation of animations is not possible with this version. This switch only affects external U3D files with pre-defined animations.)

Description

Each 3D figure is described by a Caption and a Description.


The Caption will be rendered in bold font and shall be rather short since it must fit in one line.

The length of the Description (which will be rendered in normal text) is only limited by the remaining space of the page. It can include line breaks.

The following image shows an example of a complete PDF page with an active 3D figure as rendered by the Adobe Reader XI.

Newe (2015). "Fancy article title". Journal.

Additional File S1 - Interactive 3D PDF



Model of an anatomic structure.

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Maecenas porttitor congue massa. Fusce posuere, magna sed pulvinar ultricies, purus lectus malesuada libero, sit amet commodo magna eros quis urna.

Nunc viverra imperdiet enim. Fusce est. Vivamus a tellus.

Pellentesque habitant morbi tristique senectus et netus et malesuada fames ac turpis egestas. Proin pharetra nonummy pede. Mauris et orci.

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Maecenas porttitor congue massa. Fusce posuere, magna sed pulvinar ultricies, purus lectus malesuada libero, sit amet commodo magna eros quis urna.

Nunc viverra imperdiet enim. Fusce est. Vivamus a tellus.

Pellentesque habitant morbi tristique senectus et netus et malesuada fames ac turpis egestas. Proin pharetra nonummy pede. Mauris et orci.

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Maecenas porttitor congue massa. Fusce posuere, magna sed pulvinar ultricies, purus lectus malesuada libero, sit amet commodo magna eros quis urna.

Nunc viverra imperdiet enim. Fusce est. Vivamus a tellus.

Pellentesque habitant morbi tristique senectus et netus et malesuada fames ac turpis egestas. Proin pharetra nonummy pede. Mauris et orci.

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Maecenas porttitor congue massa. Fusce posuere, magna sed pulvinar ultricies, purus lectus malesuada libero, sit amet commodo magna eros quis urna.

Nunc viverra imperdiet enim. Fusce est. Vivamus a tellus.

Pellentesque habitant morbi tristique senectus et netus et malesuada fames ac turpis egestas. Proin pharetra nonummy pede. Mauris et orci.

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Maecenas porttitor congue massa. Fusce posuere, magna sed pulvinar ultricies, purus lectus malesuada libero, sit amet commodo magna eros quis urna.

Hints

- Very small objects may cause trouble as regards the calculation of View properties. This is caused by floating point tolerance: the internal calculation is much more precise than the renderer in Adobe Acrobat. However, this should only apply for very tiny objects, so if this problem occurs, try to scale up all objects.
- If no view is specified, the PDF generator will create a default view. However, in the current version this is only possible if the U3D file was created with this module.